Package 'DRaWR'

July 21, 2025

Title Di	scriminative	Kandom	Walk	with	Restart	
Version	1.0.3					

Author Charles Blatti [aut, cre]

Maintainer Charles Blatti <blatti@illinois.edu>

Description We present DRaWR, a network-based method for ranking genes or properties related to a given gene set. Such related genes or properties are identified from among the nodes of a large, heterogeneous network of biological information. Our method involves a random walk with restarts, performed on an initial network with multiple node and edge types, preserving more of the original, specific property information than current methods that operate on homogeneous networks. In this first stage of our algorithm, we find the properties that are the most relevant to the given gene set and extract a subnetwork of the original network, comprising only the relevant properties. We then rerank genes by their similarity to the given gene set, based on a second random walk with restarts, performed on the above subnetwork.

Depends R (>= 3.0)
License GPL-2
LazyData true
Imports Matrix, ROCR, methods
RoxygenNote 5.0.1.9000
NeedsCompilation no
Repository CRAN
Date/Publication 2022-03-24 14:10:02 UTC

Contents

Index

DRaWR
RWR
hreeCol2listMat
hreeCol2MaxMat
ransmat

2 DRaWR

Description

This function runs the DRaWR two stage random walk with restart method.

Usage

```
DRaWR(possetfile = "extdata/sample.setlist", unifile = "extdata/sample.uni",
  networkfile = "extdata/sample.edge", outdir = "output_",
  restarts = c(0.7), nfolds = 1, st2keep = 1, undirected = TRUE,
  unweighted = FALSE, normalize = "type", maxiters = 50, thresh = 1e-04,
  property_types = c("allen_brain_atlas", "chip_binding", "gene_ontology",
  "motif_u5", "pfam_domain", "T1", "T2"), writepreds = 0)
```

Arguments

possetfile	(string): location of file containing location of gene sets to test.
unifile	(string): location of file listing gene universe.
networkfile	(string): location of file containing network contents.
outdir	(string): prefix of location of file to write performance results (optionally prediction results).
restarts	(vector): vector of restart values to test. Default is $c(0.7)$.
nfolds	(int): number of folds for cross validation, 1 is no cross-validation. Default is 4 .
st2keep	(int): number of property nodes to keep in second stage for each property type. Default is 50.
undirected	(bool): boolean to make network undirected.
unweighted	(bool): boolean to make network unweighted.
normalize	(string): "type" or "none". Default is 'type'.
maxiters	(int): maximum number of allowable iterations. Default is 50.
thresh	(float): threshold for L1 norm convergence. Default is 0.001.
property_types	(vector): list of possible property types. Default is c("go_curated_evidence", "go_inferred_evidence", "pfam_domain").
writepreds	(boolean): write predictions out to a file. Default is FALSE

Examples

```
DRaWR(possetfile = system.file("extdata", "sample.setlist", package="DRaWR"),
unifile = system.file("extdata", "sample.uni", package="DRaWR"),
networkfile = system.file("extdata", "sample.edge", package="DRaWR"),
outdir = "exampleRun_", restarts = c(.7), nfolds = 1, st2keep = 1,
undirected = TRUE, unweighted = FALSE, normalize = "type", maxiters = 50,
thresh = 0.0001, property_types = c("T1", "T2"), writepreds = 0)
```

RWR 3

Description

This function runs a random walk with restart using two supported matrix representations.

Usage

```
RWR(boolSparceMat, transmat, restart, query, startvec, maxiters, thresh)
```

Arguments

```
boolSparceMat (bool): Boolean to indicate sparce Matrix or list matrix.

transmat (sparce Matrix / list matrix): transition probabilities.

restart (float): probability of restart.

query (vector): probability of restarting at all nodes.

startvec (vector): initial probability of being at any node.

maxiters (int): maximum number of allowable iterations.

thresh (float): threshold for L1 norm convergence.
```

Value

list of 'iter':number of iterations, 'diff': L1 norm of difference, 'vec': converged probability distribution vector.

Examples

```
RWR(boolSparceMat=TRUE, transmat=transmat, restart=.3, query=c(rep(0.1,10),rep(0,5)), startvec=rep(1/15,15), maxiters=10, thresh=0.001)
```

```
threeCol2listMat threeCol2listMat
```

Description

This function takes a three vectors of equal length (source nodes, target nodes, and edge weights) and return the adjacency matrix as a list of vectors.

Usage

```
threeCol2listMat(a = c("a", "b", "c", "c"), b = c("a", "b", "b", "b"), v = c(1, 2, 3, 4))
```

4 threeCol2MaxMat

Arguments

а	(vector): vector of source node names.
b	(vector): vector of target node names.
V	(vector): vector of edge weights names.

Value

list of vectors matrix representation.

Examples

```
threeCol2listMat(a = c("a","b","c","c"), b = c("a","b","b","b"), v = c(1,2,3,4))
```

threeCol2MaxMat

threeCol2MaxMat

Description

This function takes a three vectors of equal length (source nodes, target nodes, and edge weights) and return the adjacency matrix as a sparse Matrix.

Usage

```
threeCol2MaxMat(a = c("a", "b", "c", "c"), b = c("a", "b", "b", "b"), v = c(1, 2, 3, 4))
```

Arguments

```
    a (vector): vector of source node names.
    b (vector): vector of target node names.
    v (vector): vector of edge weights names.
```

Value

sparce Matrix.

Examples

```
threeCol2MaxMat(a = c("a","b","c","c"), b = c("a","b","b","b"), v = c(1,2,3,4))
```

transmat 5

transmat

Sample transition matrix.

Description

A Matrix containing the normalized transition matrix from the test network

Usage

transmat

Format

a Matrix containing the normalized transition matrix from the test network.

Index

```
\ast datasets
    transmat, 5
* matrix
    threeCol2listMat, 3
    threeCol2MaxMat, 4
* random
    DRaWR, 2
    RWR, 3
* restart
    DRaWR, 2
    RWR, 3
* sparce
    threeCol2listMat, 3
    threeCol2MaxMat,4
* walk
    DRaWR, 2
    RWR, 3
* with
    DRaWR, 2
    RWR, 3
DRaWR, 2
RWR, 3
threeCol2listMat, 3
threeCol2MaxMat,4
transmat, 5
```